



Step by Step Guide to Setup your Aeron Forex Auto Trader

Step 1


Download **AeronForexAutoTrader.ex4** within member area.

Step 2

Now open **experts** folder, it may be located something like as:

C:\Program Files\Interbank FX Trader 4\experts
 C:\Program Files\InstaTrader\experts
 C:\Program Files\MetaTrader - Alpari (US)\experts
 C:\Program Files\MetaTrader - FXOpen\experts

Now paste **AeronForexAutoTrader.ex4** here, like this:



Great, you have successfully installed **AeronForexAutoTrader**

Step 3


Now open your **Meta Trader terminal**, and follow the steps as below:



Opened Meta Trader terminal with EURUSD Chart

Step 4


Set the chart to One Minute TimeFrame.



EURUSD chart with 1minute Time Frame

Step 5


Now double click on **AeronForexAutoTrader** within Navigator.




Step 6

You will get a window like this.

Go to the **Common** and set all options as below.



Go to the **Inputs**



To understand each above term, read the following

Activation Key

Activation Key is mandatory to work Aeron EA on your accounts, either on Demo OR on Real. You can generate activation keys for unlimited Demo accounts, but only for one Real account. It means your license is valid for only One Real but for Unlimited Demo accounts.

To generate Activation Key, logon to Member's Area


Here we are demonstrating Activation Key for a Demo Account.

Activation Key for Demo Account		Activation Key for Real Account	
You can generate keys for unlimited number of demo accounts		remember you can generate key only for one real account	
Broker Name	<input type="text"/>	Broker Name	<input type="text"/>
Account Number	<input type="text"/>	Account Number	<input type="text"/>
<input type="button" value="Generate"/>		<input type="button" value="Generate"/>	

Above snap is captured from Member's Area

Here you required **Broker Name** & **Account Number**

You can found these details on your Meta Trader as following:



Now put these details and click on Generate Button.

Activation Key for Demo Account		Activation Key for Real Account	
You can generate keys for unlimited number of demo accounts		remember you can generate key only for one real account	
Broker Name	<input type="text" value="IBFX"/>	Broker Name	<input type="text"/>
Account Number	<input type="text" value="5528351"/>	Account Number	<input type="text"/>
<input type="button" value="Generate"/>		<input type="button" value="Generate"/>	

After click you will get something like this:

Activation Key for Demo Account		Activation Key for Real Account	
You can generate keys for unlimited number of demo accounts		remember you can generate key only for one real account	
Broker Name: IBFX Account Number: 5528351 Key: 5531173		Broker Name <input type="text"/> Account Number <input type="text"/> <input type="button" value="Generate"/>	
<input type="button" value="Another Key"/>			

Now copy & paste the key as:

The screenshot shows the 'Inputs' tab of the 'AeronForexAutoTrader_r9.02' window. A table lists various variables and their values. The 'ActivationKey' variable is highlighted with a red circle, showing the value '5531173'. Other variables include Hedging (true), MaxTrades (10), AutoLots (true), Lots (0.1), CheckFreeMargin (true), TakeProfit (19.0), and Stoploss (1000.0). Buttons for 'Load', 'Save', 'OK', 'Cancel', and 'Reset' are visible at the bottom.

Variable	Value
ab ActivationKey	5531173
Hedging	true
123 MaxTrades	10
AutoLots	true
1/2 Lots	0.1
CheckFreeMargin	true
1/2 TakeProfit	19.0
1/2 Stoploss	1000.0

Click on OK, now your EA is activated.



Hedging (True/False)

If your broker doesn't allow hedging, then you should set it FALSE. But we recommend to use Aeron EA with brokers, who provide hedging, because its results are very nice with hedging.

Working of hedging feature:

Suppose Aeron EA opened BUY position and price goes against then, it will do averaging, but in the meanwhile if it found SELL signals, then it will open SELL position also. So due to this your trading will remain continue, it will not halt during the averaging. You will continuously make profitable trades.

MaxTrades

It is total number of positions in one direction (buy/sell) during averaging. If you set it 5 then, it will not open more than 5 trades during averaging.

AutoLots & Lots

If it is TRUE, then it will calculate lots automatically according to your free margin. But if it is FALSE then you have to define the **Lots** parameter as you want.

CheckFreeMargin

If it is TRUE, then if it found the insufficient free margin in your account, then it will give the alert message on your EURUSD-1-Minute-Chart, that you have insufficient margin and also tell you the required margin amount, but trading will remain continue.

If it is FALSE then it will not check your account free margin, and will not give any alert message regarding the margin.

TakeProfit

You can set the TakeProfit amount in Pips here.

Stoploss

You can set the Stoploss amount in Pips here.

PositionsGap

This is the minimum number of pips between two positions in same direction during the averaging process.

TrailSL

If you want to implement Trailing Stoploss in your positions then set it TRUE.

Trail Pips

If **TrailSL** is set as true, then you can specify the number of pips after that you want to trail your position.



Remember this Smile
Face must be like this

*Wish you Luck !!!
Happy Trading !!!*